# Exemplo 2. Distribución Live SystemRescueCD. Acceso mediante SSH ao disco duro dun host arrancado con SystemRescueCD

## Exemplo 2. Distribución Live SystemRescueCD. Acceso mediante SSH ao disco duro dun host arrancado con SystemRescueCD

NOTA: Empregando a distribución Live SystemRescueCD podemos acceder por SSH ao disco duro de calquera host (equipo con conexión de rede).

◊ Arrancar SystemRescueCD no host ao cal queremos acceder por SSH á información do seu/s disco/s duro/s:

<ul> <li>Linux kernel-2.6.31 (with ext4, reiser4, btrfs filesystems support)</li> <li>Both 32bits (IA32) and 64bits (AHD64/EM64T) are supported</li> <li>GParted graphical partitioning tool (partition magic clone)</li> <li>File systems tools (cet3, ext4, reiserfs, ntfs, btrfs,) and LUHZ</li> <li>Disk tools (parted, sfdisk, partimage, fsarchiver, testdisk, photorec)</li> </ul>	<pre>:: Scanning for firewire::sbp2 :: Scanning for mdadm::raid0 :: Scanning for mdadm::raid1 :: Scanning for mdadm::raid156 :: Scanning for mdadm::raid160 &gt; Performing the metwork configuration &gt; Activating mdev &gt; Making tmpfs for /newroot &gt;&gt; Attempting to mount media:- /dev/sr0 &gt;&gt; Hedia found on /dev/sr0 &gt;&gt; Loading keymaps Flease select a keymap from the following list by typing in the second second</pre>
<ul> <li>Ntfs-3g (ntfs full read-write support) and ntpass (reset windows passwords)</li> <li>Metwork tools (samba, nfs, ssh, lftp, tcpdump,) and wireless drivers</li> <li>Metwork booting via PXE (press F6 for help)</li> </ul>	name or number. You should prefer the name to the number (for type 'fr' instead of '16'). Hit Enter for the default 'us' key
<ul> <li>X.Org / Xfbdev graphical environments with XFCE and Firefox-3.5</li> <li>Hardware autodetection and Midnight Commander</li> </ul>	1 azerty 2 be 3 bg 4 br-a 5 br-1 6 by 8 croat 9 cz 10 de 11 dk 12 dvorak 13 es 15 fi 16 fr 17 gr 18 hu 19 il 20 is 22 jp 23 la 24 lt 25 mk 26 nl 27 no
==> Press P5 for help if you have boot problems with SystemRescueCd <== Welcome to SystemRescueCd for x86 (i486+amd64) - version 1.3.5	29 pt 30 ro 31 ru 32 se 33 sg 34 sk-y 36 slovene 37 trf 38 trq 39 ua 40 uk 41 us 43 fr_CH 44 speakup 45 cs_CZ 46 de_CH 47 sg-lat1 48 fr-be
F2.F3.F4.F5.F6.F7 for boot options and more help. Enter to boot. boot: _	default choice (US keymap) will be used if no action within 26 << Load keymap (Enter for default): 13_

#### a. Arrancar SystemRescueCD

b.	Elixir	teclado	español	(opción 13)	

* Starting local [ ok ]	
http://www.sysrescol.org/	
<ul> <li>Type met-setup eth0 to specify ethernet configuration.</li> <li>If your PC is on an ethernet local network, you can configure by hand: <ul> <li>ifconfig eth0 192.168.x.a (your static IP address)</li> <li>route add default gu 192.168.x.b (IP address of the gateway)</li> </ul> </li> <li>To be sure there is an ssh server running, type /etc/init.d/sshd start. <ul> <li>You will need to create an user or to change the root password with passwd.</li> </ul> </li> <li>Available console text editors : nano, vin, genacs, joe.</li> <li>Web browser in the console: elinks unu.web-site.org.</li> <li>WaNNING : Never mount anything on /mnt! It would freeze the system. <ul> <li>Use mkdir /mmirmadir and mount on /mmir/mydir instead.</li> <li>Ntfs-3g : If you need a full Read-Write NTFS access, use Ntfs-3g.</li> </ul> </li> </ul>	Details for network interface eth0 are shown below. Interface name: eth0 MMC address: 00:00:27:74:36:c7 Driver: e1000 Is this the interface that you wish to configure?
<pre>Graphical environment : use either Xorg or Xfbdev. Type wizard to run the graphical environment (or startx but it may fail) X.Brg comes with Window-Maker and you can use several graphical tools: - Partition manager: .gparted - Web browsers:firefox-3.5 - Text editors:gvim and geany rootResysteeced /root × met-setup eth0_</pre>	C No >

### c. Configurar a tarxeta de rede eth0

#### d. Detalles interface eth0

interfa	ice only. Choose one option: 1 My network is wireless 2 My network is wired	I Use DHCP to auto-detect my network setting:     Specify an IP address manually
	Cancel>	Cancel>

#### e. Opción 2. Rede cableada

## f. Configuración da rede manualmente (NON DHCP)



g. IP: 192.168.120.100

h. Dirección Broadcast: 192.168.120.255

Flease enter a network mask for ethe:	Please enter a Gateway for eth
255.255.255.0_	
	l-
COK A Carcela	COK N Claure
CON Z Control Z	CON 7 Coance

#### i. Máscara de Subrede: 255.255.255.0

#### k. Gateway



#### I. DNS

#### m. Comprobación configuración rede interface eth0



n. Password root: toor

ñ. Comprobación funcionamento ssh

Mediante o comando *ssh -v localhost* comprobamos se o servidor S podemos conectarnos a el dende *localhost*. Como é a primeira ver o o servidor avísanos se estamos de acordo coa autenticación. Respos

debug1:	expecting SSH2_MS6_KEX_DH_GEX_GROUP
debug1:	SSH2_MSG_KEX_DH_GEX_INIT_sent
debug1:	expecting SSH2 MSG KEX DH GEX REPLY
The auth	menticity of host 'localhost (127,0,0,1)' can't be established.
RSA keu	fingerprint is 0c:08:12:1e:81:14:3a:df:cb:cc:c5:36:09:b9:38:c8.
Are you	sure you want to continue connecting (yes/no)? yes
Warning:	Permanently added 'localhost' (RSA) to the list of known hosts.
debug1:	ssh rsa verifu: signature correct
debug1:	SSHZ MSG NEWKEYS sent
debug1:	expecting SSHZ MSG NEWKEYS
debug1:	SSH2 MSG NEWKEYS received
debug1:	SSH2 MSG SEBUICE REQUEST sent
debug1:	SSH2 MSG SERVICE ACCEPT received
debug1:	Authentications that can continue: publickey, keuboard-interactive
debug1:	Next authentication method: nublickeu
debug1:	Truing private keu: /root/.ssh/identitu
debug1:	Truing ariuate key: /root/.ssh/id rsa
debug1:	Truing private key: /root/.ssh/id_dsa
debug1:	Next authentication method: keuboard-interactive
Passuord	a construction method a segurate interactive
debug1:	Authentication succeeded (keubnard-interactive)
debug1:	channel 0: new [client-session] >
debug1:	Remuesting na_mare_ceptioneneth com
debug1 -	Potenting interactive second
moot Reus	present years y
e dia difatija	A CONTRACT OF CONTRACT.

## Conexión mediante o cliente liña de comandos ssh

NOTA: Considérase que o servidor SSH da distribución Live CD ten a configuración por defecto: Porto 22, Permisos de Conexión para root e Non Redireccionamento X.

Acceder a un terminal Linux e proceder como se comenta nas seguintes imaxes:

		ି ଦ୍ୱା ubuntu@ubuntu: ~	
		Archivo Editar Ver Terminal Ayuda	
		ubuntu@ubuntu:~\$ sudo ifconfig eth0 192.168.120.101/24	
0	ubuntu@ubuntu: ~ 📃 🗖 🗄	PING 192.168.120.100 (192.168.120.100) 56(84) bytes of data.	
Archivo E	ditar <u>V</u> er <u>T</u> erminal Ay <u>u</u> da	64 bytes from 192.168.120.100: icmp_seq=1 ttl=64 time=5.69 ms 64 bytes from 192.168.120.100: icmp_seq=2 ttl=64 time=0.886 m	IS
ubuntu@ubu	ntu:~\$ ifconfig -a	A 102 169 120 100 ping statistics	
	Direc. inet:10.0.2.15 Difus.:10.0.2.255 Másc:255.255.255.0 Dirección inet6: fe80::a00:27ff:fedf:14f2/64 Alcance:Enlace ACTIVO DIFUSIÓN FUNCIONANDO MULTICAST MTU:1500 Métrica:1 Paquetes RX:28 errores:0 perdidos:0 overruns:0 frame:0 Paquetes TX:64 errores:0 perdidos:0 overruns:0 carrier:0 colisiones:0 long.colaTX:1000 Bytes RX:8195 (8.1 KB) TX bytes:7820 (7.8 KB) Interrupción:11 Dirección base: 0xd020	2 packets transmitted, 2 received, 0% packet loss, time 1001m rtt min/avg/max/mdev = 0.886/3.291/5.696/2.405 ms ubuntu@ubuntu:~\$ ■	5
lo	Link encap:Bucle local Direc. inet:127.0.0.1 Másc:255.0.0.0 Dirección inet6: ::1/128 Alcance:Anfitrión ACTIVO LOOPBACK FUNCIONANDO MTU:16436 Métrica:1 Paquetes RX:4 errores:0 perdidos:0 overruns:0 frame:0 Paquetes TX:4 errores:0 perdidos:0 overruns:0 carrier:0 colisiones:0 long.colaTX:0 Bytes RX:240 (240.0 B) TX bytes:240 (240.0 B)		
uhun tu Quhun		b. Configuramos a tarxeta de rede eth0:	
upuntugupu	ntu:~\$	IP/MS: 192.168.120.101/24.	
	en en en en de Maria de la compañía de la compañía de la de	Executar no terminal o comando:	
a. Executam	los o comando liconfig -a para ver todas as tarxetas de rede	sudo ifconfig eth0 192.168.120.1/24 se o usuario co que traballa	mo
	a este equipo.	root	
veste caso a	l tarxeta de rede que nos interesa e a <b>etnu</b>	OU ifeantin atho 100 100 100 1/04 as some a vevenis reat	
		A continueción co compando ping o2 102 168 120 100 compreher	~~~
		conexión co Servidor SSH enviando dous paquetes do comando	pir
-	ubuntu@ubuntu: ~	x ubuntu@ubuntu: ~	
Archivo Edi	itar <u>V</u> er Terminal Ayuda	Archivo Editar Ver Terminal Ayuda	
ubuntu@ubunt	tu:~\$ ssh root@192.168.120.100	root@sysresccd /root % fdisk -l	
d.	1011Y of nost '192.168.120.100 (192.168.120.100)' can't be establishe	Disk /dev/sda: 4294 MB, 4294967296 bytes	
RSA key fing Are you sure Warning: Per	gerprint is 69:2e:df:ld:63:b2:42:78:9b:60:37:f5:86:05:95:83. e you want to continue connecting (yes/no)? yes rmanently added '192.168.120.100' (RSA) to the list of known hosts.	<pre>255 heads, 63 sectors/track, 522 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes Disk identifier: 0x000b7eb9</pre>	
Last Login: root@sysres	Mon Apr 19 20:35:15 UTC 2010 from 192.168.120.101 on pts/0 ccd /root %	Device Boot Start End Blocks Id Syste /dev/sda1 * 1 492 3951958+ 83 Linux /dev/sda2 493 522 240975 5 Exter /dev/sda5 493 522 240943+ 82 Linux root@sysresccd /root % ■	m ded sv

#### c. Conexión co Servidor SSH.

d. Ver a táboa de particións do equipo (fdisk -l).

Executamos o comando **ssh root@192.168.120.100**. Como é a primeira ver que nos conectamos o servidor avísanos se estamos de acordo coa autenticación. Respostamos **yes**.

Neste caso o equipo posúe o disco duro /dev/sda

toor é a password pedida de root.

#### Conexión establecida.

· · ·	buntu@ubun	tu: ~	ć				- 0	X
Archivo Editar Ver Jerminal A	yuda							
<pre>root@sysresccd /root % mkdir re root@sysresccd /root % mount -t root@sysresccd /root % ls recup</pre>	cuperar auto /dev/ erar	sda1	recupe	rar				•
bin cdrom etc initrd.ing	lost+found	nnt	proc	sbin	sys	usr	vmlinuz	
boot dev home lib	media	opt	root	STV	tap	var		
root@sysresccd /root % pwd /root								
rootgsysrescco /root % LS /root	/recuperar		-	abda.			and damage	
bin carom etc initra.ing	Lost+round	nnt	proc	SDIN	sys	usr	VIILINUZ	
root@sysresccd /root %	Incola	opr	root	SIV		var		

#### e. Crear cartafol para acceder á información do disco duro /dev/sda

No cartafol creado, en /root, mediante o comando mkdir recuperar montamos a

partición do disco /dev/sda co comando:

mount -t auto /dev/sda1 recuperar

Co comando Is recuperar revisamos o contido do cartafol recuperar.

NOTA: A ruta completa do cartafol recuperar creado é /root/recuperar

## Conexión mediante o cliente gráfico putty para plataformas Windows e UNIX

NOTA: Considérase que o servidor SSH da distribución Live CD ten a configuración por defecto: Porto 22, Permisos de Conexión para root e Non Redireccionamento X.

Acceder a un equipo Windows co programa putty e proceder como se comenta nas seguintes imaxes:



a. Panel de Control-->Conexiones de Red.

b. Conexión de Área Local-->Propiedades.



c. Protocolo Internet TCP/IP-->Propiedades.

d. IP/MS: 192.168.120.101/255.255.255.0



e. Picar en cerrar para gardar a configuración

Basic options for your PuTTY session Specify the destination you want to connect to					
192.168.120.100	22				
Connection type: O Raw O Telnet O Riogin					
Load, save or delete a stored session Saved Sessions					
Delault Settings	Load				
Dase window on exit:	Delete				
	Basic options for your PuT Specify the destination you want to of Host Name (or IP address) 192.168.120.100 Connection type: O Raw O Telnet O Rilogin @ Load, save or delete a stored session Saved Sessions Default Settings Default Settings Close window on exit: O Always O Never O Drik				

f. Dobre click na icona do escritorio putty para lanzar putty



**h. Conectando...** Como é a primeira vez que nos conectamos o serv estamos de acordo coa autenticación. Prememos en **Sí**.

g. Simplemente temos que por a dirección IP ou Host Name do servidor SSH e picar en *Open*. A conexión establecerase no Porto por defecto para a conexión SSH: o porto 22



**i. Petición de login e password**. Establecemos a conexión co usuario **root**, coa password **toor**, que modificamos anteriormente.

k. Ver a táboa de particións do equipo (fdisk -l).

**Conexión establecida**. Agora xa temos unha consola remota da distribución **SystemRescueCD** mediante unha conexión **SSH** 





## I. Crear cartafol para acceder á información do disco duro /dev/sda

No cartafol creado, en /root, mediante o comando mkdir recuperar montamos a

partición do disco /dev/sda co comando:

mount -t auto /dev/sda1 recuperar

Co comando *Is recuperar* revisamos o contido do cartafol recuperar.

NOTA: A ruta completa do cartafol recuperar creado é /root/recuperar

--ricardofc [27/04/10]